

WILDS OF WALL STREET™

GAME RULES

VERSION:	0.6
VERSION DATE:	26th August 2019
CREATED BY:	Philippe Neguembor (Game Producer)
OWNED BY:	Philippe Neguembor (Game Producer)
APPROVED BY:	Kevin Corti (Head of Product)
CONFIDENTIALITY	Proprietary

The information contained within this Document is private and confidential. Unless otherwise noted or with the prior written permission of the directors, all materials, including images, illustrations, designs, icons, photographs and written materials that appear as part of this Document (collectively, the “Contents”) are copyrights, trademarks and/or other intellectual properties owned, controlled or licensed by Spearhead Ltd. The contents of this Document may not be reproduced, published, distributed, displayed, modified or exploited in any way and remain the sole property of Spearhead Ltd.

CHANGELOG

VERSION	DATE	WHO	CHANGE SUMMARY
0.0.1	25/06/2019	PN	Document created
0.0.2	22/07/2019	PN	Updated content
0.0.3	23/07/2019	PN	Updated content and formatting
0.4	06/08/2019	KC	Minor changes as requested by iTech
0.5	06/08/2019	PN	Updated Game Rules content
0.6	26/08/2019	PN	Added Translation Terms

TABLE OF CONTENTS

<u>1.0</u>	<u>DOCUMENT SCOPE</u>
<u>2.0</u>	<u>GAME RULES</u>
	<u>2.1 DESCRIPTION</u>
	<u>GAME MECHANICS</u>
<u>3.0</u>	<u>PAYTABLE</u>
	<u>3.1 SYMBOLS</u>
	<u>3.2 PAYLINES</u>
<u>4.0</u>	<u>GAME FUNCTIONS</u>
	<u>4.1 USER INTERFACE</u>
	<u>4.2 POP-UP MENUS</u>
<u>5.0</u>	<u>GAME SETTINGS AND REGULATORY</u>
	<u>5.1 CURRENT TIME</u>
	<u>5.2 REALITY CHECK</u>
	<u>5.3 ADDITIONAL INFORMATION</u>
<u>6.0</u>	<u>GAME VERSIONS</u>
<u>7.0</u>	<u>MATH MODEL</u>
<u>8.0</u>	<u>TECHNICAL INFORMATION</u>
<u>9.0</u>	<u>ADDITIONAL INFORMATION</u>

1.0 DOCUMENT SCOPE

The contents of this document serve to accurately describe the form, function, and characteristics of the game known as *Wilds Of Wall Street*™.

2.0 GAME RULES

2.1 DESCRIPTION

Wilds Of Wall Street™ is a video slot set up in the greedy world of trading in the 90's. The game features side-bets, bet-ups and a “buy into bonus” feature (Not available in some jurisdictions).

The game is played with five reels and 15 paylines - which can expand up to 65 paylines as the game progresses - paying from left to right.

The Free Spins Mode is played with five reels, with five symbols displayed on each, and 5 paylines paying either from left-to-right or right-to-left depending on the result of the directional wild.

The player selects a bet amount using the bet amount button on the main game screen.

Autoplay automatically plays the game with the selected number of rounds.

RTP: 96.50% (not affected by Insider Tip feature)

1.2 GAME MECHANICS

RTP: 96.50%

Base Mode

- Wilds Of Wall Street is a 5x5 videoslott.
- The player is paid from left to right for matches of 3 or more symbols landing on a payline (see Paytable).
- Simultaneous or coinciding wins on different paylines are added.
- Any win triggers a free respin.
- Six consecutive wins triggers the Free Spins Mode.
- Some of the slots in the reelset are initially hidden and inactive.

- With every respin some symbols are revealed. This increases the number of active paylines.
- The blocks are cleared in the following order:
 - 1x3x5x3x1 - Initial state - 15 paylines
 - 3x3x5x3x1 - After 1 win - 25 paylines
 - 3x3x5x3x3 - After 2 wins - 35 paylines
 - 3x5x5x5x3 - After 3 wins - 45 paylines
 - 5x5x5x5x3 - After 4 wins - 55 paylines
 - 5x5x5x5x5 - After 5 wins - 65 paylines

4	3		3	5
1				2
1				2
4	3		3	5

- If a re-spin does not result in a win the game will revert to the initial state.
- The player can optionally use the Insider Tips feature which reveals additional symbols - as if win(s) have already happened - for a cost which is proportional to the bet amount.
- The Insider Tips are unlocked by collecting Wilds on the reels in Base Mode.
- A visual meter indicates progress towards unlocking each Insider Tip. This is specific to each Bet Level. If the player changes Bet Level, the meter resets. If the player returns to a previous Bet Level, the meter will show the previously-stored progress.
- The amount of Wilds necessary to unlock each Insider Tip button are shown below:

INSIDER TIP	WILDS NEEDED
1	12
2	48
3	140

- The cost of an Insider Tip is based on a multiplier (see table below) applied to the current line bet amount.

INSIDER TIP	MULTIPLIER
1	37
2	70
3	134

- The player can opt to pay to trigger Free Spins, using the “Buy Into Bonus” button (Not available in some jurisdictions).
- The cost of Buy Into Bonus is 36 times the current bet amount.

Free Spins Mode

- Free spins are paid according to the bet amount prior to entering Free Spins Mode.
- The reelset in the Free Spins Mode is 5x5. There are no blocked symbols.
- The reelset has 5 straight horizontal paylines, that allow wins both ways (see Paytable)
- 1st, 2nd, 4th and 5th reels only contain high-paying symbols.
- The 3rd reel contains only Directional Wilds and bell symbols.
- Directional Wilds substitutes for all paying symbols, but only for the direction shown, blocking any win in the opposite direction.
- The Bear Wild symbol allows left-to-right wins, and the Bull Wild symbol allows right-to-left wins.
- The pay direction changes randomly every spin. After the reels land, the marker at the top of the reelset indicates ‘the Market Outcome’ and signals the direction that will be paid (Bear or Bull)
- A history of the 10 latest Market Outcomes is displayed at the top of the reelset.
- Before every spin, the user can opt to Bet on a Market by pressing either the Bear button or Bull button. If the Market Outcome is the same as the market selected, any winnings are doubled. Betting On A Market does not void any winnings for the opposite direction.
- The cost of Betting On A Market is 25 times the line bet amount.
- The player is granted an unlimited number of free spins.

- The Free Spins counter displays elapsed free spins.
- Up to one Bell can land per spin and Free Spins end when 3 Bell symbols have landed throughout spins. The Bell Counter at the top of the reelset displays how many bells remain.
- If the player has only one bell left they can opt to pay for Bell Insurance. This voids any bell landing in the next spin. Bell Insurance can be used only once per Free Spins Mode session.
- The cost of the Bell Insurance side-bet is 50 times the line bet amount.

3.0 PAYTABLE

3.1 SYMBOLS

There are eleven different symbols in *Wilds Of Wall Street's* Base Mode:

- The wild
- Six high-paying symbols
- Five low-paying symbols

WILD



Substitutes for any other symbol. When landing on the reel set, it increments the Insider Tips meter.

Symbol win values (for bet amount of 15.00, for example). Actual payouts are based on the player's bet amount.

JET	HELICOPTER	YACHT	SPORTS CAR
			
x5 10 000	x5 1 000	x5 500	x5 250
x4 1 000	x4 250	x4 125	x4 100
x3 250	x3 100	x3 60	x3 50

WILDS OF WALL STREET™ - GAME RULES

WATCH



x5 **200**

x4 **80**

x3 **40**

BUST



x5 **150**

x4 **60**

x3 **30**

A



x5 **100**

x4 **40**

x3 **20**

K



x5 **100**

x4 **40**

x3 **20**

Q



x5 **50**

x4 **20**

x3 **10**

J



x5 **50**

x4 **20**

x3 **10**

10



x5 **50**

x4 **20**

x3 **10**

- In Free Spins only high-paying symbols are used (on reels 1, 2, 4 & 5).
- Directional Wilds and the Bell symbol appear only on the 3rd reel.

BEAR WILD



Substitutes for any other symbol to grant a win in a left to right direction.

BULL WILD



Substitutes for any other symbol to grant a win in a right to left direction.

BELL




Free Spins Mode session is over when a total of 3 bells land on the reels throughout the spins.

3.2 PAYLINES

Base Mode

The game starts with 15 paylines, paying for matches of 3 or more symbols from the furthestmost left reel to the furthestmost right one. With every win, symbols on the reelset are unlocked, granting more paylines.

Initial State





10



11



12



13



14



15



After 1 win

16




17



18




19




20



21



22




23



24



25



After 2 consecutive wins

26



27



28



29




30



31



32



33



34



35



After 3 consecutive wins

36



37



38



39



40



41



42



43



44



45



After 4 consecutive wins

46




47



48



49



50



51



52



53



54




55




After 5 consecutive wins

56




57



58



59




60




61



62



63



64




65



Free Spins Mode

There are only 5 paylines in the Free Spins Mode, paying for matches of 3 or more matching symbols, from either the furthestmost left to the furthermore right reel or the furthestmost right to the furthestmost left reel. The pay direction alternates randomly on each spin.



4.0 GAME FUNCTIONS

4.1 USER INTERFACE

The table below describes the behaviour of the user interface buttons in the game.

SPIN BUTTON

Click to start a game round at the current bet value.



SPIN BUTTON (DURING SPIN)

Click to rapidly stop the reel animations or any win animations. This does not stop autoplay.



AUTOPLAY BUTTON

Click to open the autoplay pop-up menu.



AUTOPLAY BUTTON (WITH AUTOPLAY ACTIVE)

The number displays how many autoplay spins remain.
Click to stop autoplay.



BET AMOUNT BUTTON

Click to open the bet amount pop-up menu.



TURBO BUTTON

Click to switch between high and low spin speed.



OPEN INSIDER TIPS

Press to display the Insider Tips Menu.



CLOSE INSIDER TIPS

Replaces the Insider Tips Menu Show button when the Insider Tips Menu is on display. Press to hide the Insider Tips Menu.



INSIDER TIPS METER

Indicates the number of gathered Wilds and the range to activate the different Insider Tips.



INSIDER TIPS 1 (INSIDER TIPS MENU)

Press to clear blocks on the reelset simulating a win. The cost of this feature is displayed next to the button.



INSIDER TIPS 2 (INSIDER TIPS MENU)

Press to clear blocks on the reelset simulating 2 consecutive wins. The cost of this feature is displayed next to the button.



INSIDER TIPS 3 (INSIDER TIPS MENU)

Press to clear blocks on the reelset simulating 3 consecutive wins. The cost of this feature is displayed next to the button.



BUY INTO BONUS (INSIDER TIPS MENU) (Not available in all jurisdictions)

Press to advance directly to the Free Spin Mode. The cost of this feature is displayed inside the text area of the button.



INFO (INSIDER TIPS MENU)

Press to see the Insider Tips info menu



BEAR BUTTON (FREE SPINS MODE)

Press to bet that the pay direction for the next spin will be left to right. If correct, winnings are doubled. The cost of the bet is displayed under the button.



BULL BUTTON (FREE SPINS MODE)

Press to bet that the pay direction for the next spin will be right to left. If correct, winnings are doubled. The cost of the bet is displayed under the button.



BELL INSURANCE (FREE SPINS MODE)

Press to void any bell landing on the next spin. The button only appears when there is only one bell left to leave the Free Spins Mode. If pressed, at the end of the spin, the button will be hidden for the remainder of the Free Spins Mode session. The cost of this feature is displayed next to the button.



MENU BUTTON

Click to open the settings, payable and game rules.




AUDIO BUTTON

Click to toggle all audio on/off.



4.2 POP-UP MENUS

Bet amount



The bet amount pop-up menu displays all available bet amounts. The currently-selected amount is highlighted white. If the player clicks on a different amount, the menu is then hidden and the newly-selected bet amount is now displayed in the main game screen. The player can also click on the 'Back' icon, to return to the main game screen without making any changes to the bet amount.

Autoplay



The autoplay pop-up menu allows the player to select a number of spins to autoplay. To do so, the player clicks on one of the available spin number options. This button will then highlight white. The player must then set a loss limit (must be greater than 0) and then click on the spin button to confirm their intention. The menu is then hidden and the player is returned to the main game screen, with autoplay active.

The player may also choose to set optional conditions to automatically stop autoplay. These include:

- Stop autoplay on a single win of a player-stipulated value.
- Stop autoplay if the balance increases by the amount the player specifies.
- Stop autoplay upon entering free spins

Note: If you are disconnected while playing, all autoplay settings will return to default when you reload the game.


General menu



Clicking on the settings hamburger icon on the main game screen allows the player to access:

- The settings menu
- The paytable
- The game rules

Settings menu



The settings menu allows the player to:

- Spin by pressing the Space Bar (disabled by default)
- Switch between normal and fast spin speed.
- Set a timed reminder (the 'Reality Check').
- Set whether the splash screen should show on loading.
- Mute all audio
- Change the music volume.
- Change sound effects volume.
- Change the graphics quality

When played in a mobile browser, the game settings also include an option to modify the orientation of some aspects of the UI for left, right or center viewing. This includes the spin, bet level

and autoplay buttons on the main game screen, and also some aspects of the settings pop-up menu.

5.0 GAME SETTINGS AND REGULATORY

5.1 CURRENT TIME

The game client shows the current time at all times (in the bottom left of the screen). The time is acquired from the player's computer or device system clock.

5.2 REALITY CHECK

In case the operator does not provide this functionality, the player can choose to set a reminder for 30, 60 or 90 minutes from the settings menu.

To access this, the player:

1. Clicks/taps on the 'setting hamburger' icon.
2. The settings, payable, game rules, and close icons pop-up from the bottom of the screen. On mobile, the home and mute buttons are also visible.
3. The player clicks/taps on the settings icon.
4. The settings pop-up menu is displayed.
5. Under 'Set Reminder', the player can select one of three possible options are enabled (30, 60 and 90 minutes).
6. The player clicks/taps on 'Close' to return to the game.
7. If the player is still playing after their chosen interval has been reached, then a pop-up is displayed with a text reminder and the stated time interval. The pop-up screen contains:
 - a. Notice of selected reminder time interval having been reached
 - b. Link to return to the game
 - c. Link to exit the game

5.3 ADDITIONAL INFORMATION

The following processes may be subject to the terms and conditions of the gaming site.

- The process of managing unfinished game rounds.
- The time after which inactive game sessions are automatically ended.

In the event of malfunction of the gaming hardware/software, all affected game bets and payouts are rendered void and all affected bets refunded.

6.0 GAME VERSIONS

Game ID: *WildsOfWallStreet*



Fig 1: Desktop game screen



Fig 2 & 3: Mobile portrait & landscape game screens

7.0 MATH MODEL

NUMBER OF REELS:	5
NUMBER OF COINS:	1
NUMBER OF PAYLINES:	Ranges from 15 to 65 in Base Mode, 5 in Free Spins Mode
DENOMINATIONS:	0.15, 0.30, 0.60, 0.90, 1.20, <u>1.50</u>, 3.00, 4.50, 15.00, 30.00, 45.00, 75.00, 90.00 and 150.00
MINIMUM BET***	0.15
MAXIMUM BET***:	150.00
MAXIMUM EXPOSURE***:	216,000
VOLATILITY:	High
DEMO GAMEPLAY AVAILABILITY:	Yes

- *Maximum exposure is a hard limit enforced by the game platform*
- A currency value is marked with asterisks (***) next to the caption in all tables.
- Values in **bold** can be changed by the operator.
- Underlined and **bold** values are default settings when there is a limited set of options for a setting.
- All currency values relate to a currency multiplier of 1 which is accurate for EUR, USD, and GBP. For other currencies, another multiplier might be used. For example: SEK has currency multiplier 10. All values related to currency should thus be multiplied by 10 for SEK. I.e. 10€ = \$10 = £10 = SEK100.
- For denomination based games such as video pokers and slot machines, the maximum win is based on the maximum bet which is the coins x lines (hands) x max denomination. The max denomination is not always turned on by default, so the default maximum win may be lower than stated.

Return to player configurations

BASE GAME	42.85%
FREES PINS	53.65%
TOTAL	96.50%

8.0 TECHNICAL INFORMATION

NATIVE RESOLUTION	1920x1080
NATIVE ASPECT RATIO	16:9
TECHNOLOGY	JavaScript/HTML5
HTML5 CANVAS SUPPORT	YES
WEBGL SUPPORT	YES
DESKTOP BROWSER	YES
TABLET BROWSER	YES
MOBILE BROWSER	YES

9.0 ADDITIONAL INFORMATION

Translations of Game Terminology

Note: The following table is only applicable if you are playing in a language other than English.

ENGLISH TERM	TRANSLATED TERM
Wild	Wild
Big Win	Big Win
Super Win	Super Win
Mega Win	Mega Win
Epic Win	Epic Win